How to Stream & Multistream on Mobile (Easy Guide)

Streaming & Lovense · https://help.fansyme.com/docs/live/how-to-stream-multistream-on-mobile-easy-guide/

This post is also available in: Deutsch (German)

This guide shows you how to go live on **FansyMe** using your phone, step by step. Take your time. Follow each step in order.

Step 1 — Get the App

If you have an Android phone (Samsung, etc.):

1. Open the **Play Store** app.
2. Type **"SplitCam"** in the search box.
3. Tap **Install**.

If you have an iPhone:

1. Open the **App Store** app.
2. Type **"SplitCam"** in the search box.
3. Tap **Get**.


After it installs, open the app. It will ask to use your **camera** and **microphone**. Tap **Allow** for both. You need this to go live.

Step 2 — Get Your FansyMe Stream Info

1. Log in to your **FansyMe** account (on your phone browser or the FansyMe app).
2. Click on **Go Live**
3. Select the **Settings** (Gear Icon) Icon next to the Menu
4. Click **Get OBS Key**

5. You will see two things:
   - **Stream URL** (a web address)
   - **Stream Key** (a long code, like a password)
6. Copy both. You will need them in the next step.

⚠ **Important:** Never show your Stream Key to anyone. It is like a password. If someone else has it, they can stream on your channel.



Find your Stream URL and Stream Key in your FansyMe dashboard.

Step 3 — Add FansyMe Inside SplitCam


FansyMe is not one of the big, famous platforms (like Chaturbate or CamSoda), so it does not have its own picture/logo button in the app. This is normal — it just means you add it a slightly different way, using something called **Custom Server**. It works exactly the same as the other platforms, just one extra step.

1. In SplitCam, go to **Channel Settings**.
2. Tap **Choose Channel**.
3. At the bottom of the list, tap **Custom Server**.
4. Fill in the boxes:


- **Stream Name:** type `FansyMe` (this is just a nickname so you remember it)
- **Stream URL:** paste the Stream URL you copied from FansyMe
- **Stream Key:** paste the Stream Key you copied from FansyMe

5. Tap **Save**.


Now "FansyMe" will show up on your Channel Settings screen, under **Active**.



Click on add new channel to add FansyMe.


10:57
1h
Back
Choose Channel
Chaturbate
Chaturbate
CamSoda
CamSoda
BongaCams
BongaCams
CAM4
Cam4
streamate
Streamate
AVN
STARS
AVNStars
amateur.tv
Amateur
Custom Server
Want your web site listed here?

Tap Custom Server since FansyMe isn't listed by name yet.



10:56
1h
65
Back
Edit Channel
Save
Custom Server
Stream Name
FansyMe
Stream URL
rtmps://live.cloudflare.com:443/live/
Stream Key
8ed940bc16125b4ad6e107ff2aa0561fkc567d7691...
Delete channel
All saved data will be deleted automaticly.
We will setup the default settings.

Screenshot

Step 4 — Set Your Video Quality

On the Channel Settings screen, you will see three boxes. Set them like this:

Setting	What to choose
Resolution	HD 1080i
FPS	30 FPS
Quality	5 Mb/s (if your internet is slow, choose a lower number)



Set Resolution to HD 1080i, FPS to 30, and Quality to 5 Mb/s.

Step 5 — One Very Important Setting


1. Tap **Advanced Settings**.
2. Find the box called **Keyframe Interval**.
3. Check that it says **2**. Most phones already have this set to 2 by default — you usually don't need to change it. If it shows a different number, change it to **2**.

⚠ **This step is very important.** Always check it, even if you think it's already right. If it's wrong, your stream might connect but show no video.

Also set:

- **Profile Level:** Baseline
- **BitRate Mode:** Average
- **Restream Server:** Detect automatically

Tap **Save**.




Keyframe Interval must be 2 — check this every time."

Step 6 — Go Live

1. Go back to the main Channel Settings screen.


2. Next to FansyMe, find the switch that says **Enable this stream**. Turn it **ON** (it turns green).
3. Tap the ✓ checkmark button at the top right.
4. Start your stream from the main screen.
5. Check your FansyMe page. Make sure it shows you are live and video is playing (not just sound).


9:59
31
Channel Settings
Advanced Settings
HD 1080i
Resolution
30 FPS
FPS
High 5Mb/s
Quality
Active
1 channels
FansyMe
Custom Server
Enable this stream

Turn the switch green to enable FansyMe.

Want to Stream to More Than One Site at the Same Time?

You can repeat **Step 3** for other sites too (like Chaturbate, CamSoda, BongaCams, Cam4, Streamate). Turn on **Enable this stream** for each one you want. SplitCam will send your video to all of them at the same time.


9:59
31
Channel Settings
Advanced Settings
HD 1080i
Resolution
30 FPS
FPS
High 5Mb/s
Quality
Active
1 channels
FansyMe
Custom Server
Enable this stream
Disabled
1 channels
Chaturbate
Chaturbate
Enable this stream
Add New Channel

You can add and enable more than one platform at once.

If Something Goes Wrong

- **Stream won't connect:** Check that you copied the Stream URL and Stream Key correctly. No extra spaces.
- **Connects, but no video shows:** Check the Keyframe Interval — it must be **2**.
- **Video is choppy or freezing:** Lower the Quality number, or connect to Wi-Fi instead of mobile data.
- **App disconnects while streaming:** Plug your phone into a charger and turn off battery-saver mode before you go live.